



## Installation and running requirements of CaptureCAM™-PRO

### Default Installation Paths

**Recorder Default Path:** c:\ProgramFiles\Cintinel

**Player Default Path:** c:\ProgramFiles\Cintinel

Each time CaptureCAM™-PRO is run, a temp folder called CCPTemp and sub folders are created on the same drive that the CaptureCAM™-PRO Recorder and/or Player is installed to. Appropriate Admin rights are required for writing to and deleting this folder. The drive used for the CCPTemp folder can be changed in preferences or upon installation.

### Windows Registry

Access to the following Registry key, is vital for running CaptureCAM™-PRO Recorder and Player.

**Key** HKEY\_CURRENT\_USER

Software\Cintinel

A number of sub keys are written to throughout CaptureCAM™-PRO's operation, access to this key will be required at all times.

### Hardware Acceleration

For the CaptureCAM™-PRO Recorder to run correctly, it will turn off Hardware Acceleration during a recording session and turn it back on again after. Therefore, if a user's system is locked down so that no writing to the registry in the areas that affect Hardware Acceleration is possible, the CaptureCAM™-PRO Recorder will become "slow and unstable."

**Keys** HKEY\_LOCAL\_MACHINE

Hardware\DeviceMap\Video\

System\CurrentControlSet\Services\

HKEY\_CURRENT\_CONFIG

System\CurrentControlSet\Services\

### ConfigSetup.ini

We have provided a special file that you can use to configure the Preferences and installation settings of both the CaptureCAM™-PRO Recorder and Player. To access and make changes to this file, simply run the Recorder or Player installer. When the the first screen appears cancel the installation. Inside the folder where you ran the installer you will find a file called "**ConfigSetup.ini**". You can open this in any text editing program and make changes.

**IMPORTANT:** The **ConfigSetup.ini** file must be in the same folder as the installer when run.

**SPECIAL NOTE:** In the **ConfigSetup.ini** file, under <<< CCPR Recorder General Settings >>>> is a "Serial Number Option". Leave this blank unless you are going to run the installer in Silent Mode.

### Silent: Install and UN-Install:

It is possible to force the CaptureCAM™-PRO "Recorder and/or Player" Installer or UN-Installer to run in silent mode by using the switch "/S". This will stop any screens and/or dialog boxes from appearing during the process and will ensure that only default settings are used. Additionally, you can also evoke a silent Install or UN-Install by creating a small batch file.

### Creating a Batch File For Silent Install OR Silent Uninstall:

1. Open Windows note pad.
2. Inside quotes, type the full file name and file path of the Installer. Outside of the quotes leave a space and type /s

**Example for Silent Install:** "c:\CaptureCAM\Install\CCPR-Setup.exe" /s

**Example for Silent Uninstall:** iun6002.exe "C:\Program Files\Cintinel\CCPV2\irunincc.ini" /s

For the CaptureCAM™-PRO Player, substitute ( CCPR-Setup.exe with CCPlayerSetup.exe) and ( irunincc.in with iruninccp.ini)

3. Save the file as "**CCP.bat**" (the name is not important, but the extension ".bat" is).
4. Once the batch file has been created, simply double click on it to run in silent mode.

**NOTE:** This example assumes a default install, where the **irunincc.ini** file was installed to the default directory(s) and the Operating System is Windows XP. CaptureCAM™-PRO's uninstaller will remove everything that the Installer created including Windows registry entries.